

for AEM Connect Plus Version 6.1.1

Table of Contents

ΑI	bout this Guide	
	Conventions	2
	Typographical	
	lcons	
1	About GlobalLink Connect	5
	Globalization Management Suite	5
	GlobalLink Connect for AEM	5
	AEMP PD Localization Workflow	5
2	Get Started	7
	Use Requirements	7
	Software Requirements	7
	Installation Prerequisites	7
	Explore the User Interface	7
	Adobe Experience Manager	8
	GlobalLink Menu	8
	GlobalLink Action Page	9
3	AEM System User Setup	10
	Create an AEM System User	10
	Assign User Permissions	10
	Create a User Mapping	12
4	AEMP Adaptor Installation	13
	Preinstallation from 5.8.x and 5.9.x	13
	Install the Adaptor	13
	Install the Touch Editor Module	14
	Configure AEM Dispatcher Module	15
	Uninstall the Adaptor	15
5	Assign Non-Admin User Permissions	16
6	AEMP Adaptor Configuration	17
	Configure General Connection Settings	17
	Configure Proxy Server Settings	19
	Configure Dashboard Appearance Settings	20
	Configure Log Setting	22
	Configure Users Setting	23
	Configure Preview Server Settings	24
	Configure Preview Server Filter	26
	Configure Workflows Setting	26

This documentation is proprietary and is protected by U.S. and international copyright laws and trade secret laws. Copyright © 2020 Translations.com, Inc. ("Translations.com") All rights reserved. No part of this documentation may be reproduced, copied, adapted, modified, distributed, transferred, translated, disclosed, displayed or otherwise used by anyone in any form or by any means without the express written authorization of Translations.com. Other names may be trademarks of their respective owners.

	Configure Permissions Setting	27
7	AEMP Site Repository Configuration	30
	Configure General Repository Settings	30
	Configure Resources Settings	32
	Configure Blocked Resources Settings	35
	Configure Tags Settings	36
	Configure Tag Repositories	38
	Configure References Settings	41
	Configure Languages Settings	43
	Configure Auto Submission Settings	45
	Configure Notifications Settings	47
	Configure DAM Assets Settings	48
	Configure DAM Repositories	50
	Configure DAM Workflow Wait Time	53
	Configure Link Rewriting Settings	54
	Configure TM Update Settings	56
	Configure Workflow Review Settings	57
	Configure Commerce Settings	59
	Extend Target Rules	
9	Workflows Configuration	62
	Create Custom Workflows	62
	Test Custom Workflow	
10	Create i18n Dictionary Repositories	67
	Configure i18n Dictionaries as JSON Files	67
11	Configure Error Notifications	68
12	Configure Adaptor Logs	69
13	Content Fragments Configuration	
	Include CMS AEM 6.3.0 Fragments	
	Include CMS AEM 6.4.0 and 6.5.0 Fragments	71
14	Experience Fragments Configuration	
	Include Experience Fragments from Page	
	Configure Experience Fragments Repositories	
15	Campaigns Configuration	
	Configure Campaign Repositories	
16	AEM Rollout Configuration	
	Create a Custom Rollout on AEM 6.3.0	
	Create a Custom Rollout on AEM 6.4.0 and 6.5.0	79

About this Guide

The images and topics contained in this guide are not representative of every GlobalLink® product installation. Each GlobalLink product installation is configured to meet the needs of the intended users, who may or may not require certain features and options. Therefore, the features and options covered in this guide may differ from those available on your GlobalLink product installation.

Conventions

Typographical

The following table explains the typographical conventions used in this guide.

Bold User interface controls, commands, and keywords in body text.

italic Represents an input field where user input is expected.

<...> Generic parameters that must be replaced by specific code or text.

Icons

The following table explains the icon conventions used in this guide.



Note:

This icon designates a note or helpful suggestion or reference relating to the surrounding text.



Best Practice:

This icon designates a suggestion for best practice relating to the surrounding text.



Alert:

This icon designates a warning or alert relating to the surrounding text. In this situation, the user should exercise caution to avoid an undesirable result.

1. About GlobalLink Connect

GlobalLink Connect serves as a bridge between your back-end systems and our industry-leading Globalization Management Suite, allowing you to use the full functionality of your CMS, DMS, e-commerce, PIM, and database platforms to manage multilingual content.

Globalization Management Suite

The GlobalLink Globalization Management Suite (GMS) is a modular set of translation technology products that provide enterprise solutions for organizations. It consists of the following server components:

- GlobalLink Project Director—An automated translation workflow system that leverages and communicates with the other GlobalLink products through a published Web services API
- GlobalLink TM Server—A robust, scalable server-based translation memory solution
- **GlobalLink Term Manager**—A web-based terminology management tool that allows any translation manager to modify, review, search, or delete existing terms
- GlobalLink TransStudio Online—A web-based translation tool that offers translators instant access to translation memories and terminology lists
- GlobalLink TransStudio Review—A web-based translation review tool with an intuitive user interface that allows translated content to be reviewed quickly and effectively
- GlobalLink Translation & Review Portal—A web-based, collaborative application that streamlines the linguistic review process

The integration with AEMP involves Web services communication between AEMP and GlobalLink Project Director (PD).

GlobalLink Connect for AEM

GlobalLink Connect for AEM, referred to as AEMP, integrates seamlessly with AEM providing the following functions:

- Support of multiple configurations
- Integration with standard and non-standard languages and structure
- · Allowing synchronization of source and target
- · Providing on-page review
- Allowing granular control of synchronization
- · Providing translation memory updating tools
- · Sending pages, tags, and binaries for translation

AEMP PD Localization Workflow

The AEM, AEMP, and Project Director (PD) interaction workflow:

- 1. A web page is created or updated in the AEM repository.
- 2. The web page is sent to PD manually from AEM using workflows through AEMP.

3. The workflow installed with the package is GlobalLink Recursive. This workflow sends the components configured on the selected page as well as all referenced pages. If you want to embed translation into a different workflow, contact your AEM support representative.

(i) Other

Other available workflows are:

- **GlobalLink Single—**The workflow only sends components configured on both the source and target page. Components that exist on the source page but not the target page are excluded.
- GlobalLink Recursive—The workflow sends those components that are configured on the selected page including, the referenced pages, and creates missing components on the target pages.
- GlobalLink Recursive Split—The workflow sends a page as well as along with all pages
 referenced on it. This action splits the file, so each page is a unique XML file while remaining a
 single submission.
- AEM 6.3+ users should continue to use the Granite versions of each workflow. And AEM 6.4 and 6.5 users should use the new adaptor workflow location built during the adaptor workflow configuration. Refer to your administrator.

2. Get Started

This section describes the AEMP installation requirements and the adaptor user interface.



All installation and configuration files are in the installation package provided by GlobalLink. You can also access the package through Adobe Experience Manager (AEM) Package Share.

Use Requirements

Use Adobe Experience Manager (AEM) to connect to Project Director (PD) with the GlobalLink AEMP adaptor. Have the following data ready before you connect AEM to PD for both staging and production server types:

- PD URL
- User name
- Password
- Project short codes
- · Default classifier



User credentials are client-specific. Do not share credentials.

Software Requirements

The requirements described must be met to complete the AEMP Adaptor installation.

Product	Versions
AEM	AEM 6.5.0 (SP1 and higher), 6.4.0 (SP1 and higher), 6.3.0 (SP1 and higher)
GlobalLink Project Director	4.19 or later
JDK	1.8.0 or later

Installation Prerequisites

You must meet these installation prerequisites before installing the adaptor:


- · Log in with system administrator privileges
- Have the AEMP adaptor package ready to install
- Create a language copy of the master site in AEM for each required language
- Map AEM users

Explore the User Interface


You can initiate and monitor content translation requests from within AEM using GlobalLink AEMP. Access AEMP by clicking the **AEM Navigation Pager**, from the **GlobalLink** menu.

Adobe Experience Manager

You can access the GlobalLink menu from both the AEM Navigation Pager—Adobe Experience Manager and the GlobalLink Translation button.




GlobalLink Menu



The available functions of the GlobalLink menu are:

- Configuration—Enter a variety of adaptor settings.
- Repositories—Enter a variety of repository settings.
- Submissions—Manage your submissions.
- TM Updates—Manage your translation memory.
- Synchronization Jobs—Align all of your non-translatable nodes.

GlobalLink Action Page



The actions on the GlobalLink menu are:

Actions Bar

- Create—Generate a submission.
- Create from CSV—Generate a submission from a CSV file.
- Clone Submission—Copy an existing submission to resend.
- Detail—Display the details for the selected submission.
- Start Submission—Export a submission to Project Director (PD).
- Re-Open—Change the submission to Sent to enable it for downloading.
- Reimport—Download a submission from PD.
- Edit—Modify a submission.
- Delete—Remove a submission from the dashboard.
- PD Statistics—Retrieve your submission statistics from PD.
- Cancel Submission—Remove the selected submission from PD.
- Archive—Move a submission from the dashboard to the archive.
- Filter—Limit the list of submissions to a select criteria.

Content List Display of all submissions.

3. AEM System User Setup

You must create, assign permissions, and map the AEM system users before installing the AEMP adaptor. If you map your system users after installation, you must reinstall the adaptor.

Create an AEM System User

To create an AEM system user:

- 1. Log in as system administrator.
- 2. Go to Content Repository Extreme at:

```
http://localhost:4502/crx/explorer/index.jsp
```

- 3. Click User Administration.
- 4. Click Create System User.



Do not click Create User by mistake.

- 5. Enter gl-service in the user ID field.
- 6. Click the green check mark at the side.
- 7. Click Close.

The system user is created.


Assign User Permissions

You must assign user permissions for each user you create.

To assign user permissions:

1. Go to:

http://localhost:4502/useradmin



2. Enter gl-service in the search field.


- 3. Double-click **gl-service** to open the user information properties.
- 4. On the **Permissions** tab, select only the **Read** permission for the root folder.




5. Select the **Modify**, **Create**, and **Delete** permissions for the other folders in the root folder.


For first-time adaptor installations, provide full permissions to /apps/. You can change to specific nodes after adaptor installation.

• Update the permissions for the /apps/globallink-adaptor/ node immediately after completing installation.




Select permissions for /content/ and, or necessary sub-nodes, such as the, we-retail site





- · Permissions for workflows:
 - If AEM 6.3—Select permissions for /etc/workflow/models/globallink-adaptor/ and /etc/workflow/models/instances/

- **If AEM 6.4 or 6.5**—Select permissions for /var/workflow/models/globallink-adaptor/ and /var/workflow/models/instances/
- Permissions for tags:
 - If AEM 6.3—Select /etc/tags/ or necessary sub-nodes, such as, we-retail site.
 - If AEM 6.4, 6.5 or higher—Select /content/cq:tags/ or necessary sub-nodes, such as, we-retail site.



6. Click Save.

The user is assigned the new permissions and added to the **Repository** folder.

Create a User Mapping

To create a user mapping:

1. Go to Web Console Manager at:

```
http://localhost:4502/system/console/configMgr/
```

- Search for Apache Sling Service User Mapper Service.
- 3. Click + and add the following to Service Mappings:

```
gs4tr-globallink-adaptors-aem-bundle:gl-service=gl-service
```

4. Click Save.

The new user mapping is created and saved.

4. AEMP Adaptor Installation

Preinstallation from 5.8.x and 5.9.x

This version has a new location of the Project Director (PD) connection configuration node and adaptor data in the <code>/apps/globallink-adaptor</code> folder. If you are upgrading from 5.8.x or 5.9.x, you must perform these preinstallation upgrade steps.

To upgrade your installation:

1. Backup to an AEM compatible zip package, the content of:

/libs/globallink-adaptor/config/repositories

2. Backup to an AEM compatible zip package, the content of:

/libs/globallink-adaptor/submissions


Your upgrade is complete.



The backups are used in the event of folder content loss during the upgrade.

Install the Adaptor

Before installing the adaptor, you must meet all software prerequisites. Refer to Software Requirements.



To install the adaptor:

- 1. Using the package manager, upload the GlobalLink-Connect Plus-x.x.x package to the AEM instance.
- 2. Click Install.
- 3. Go to the web console manager:

http://localhost:4502/system/console/configMgr

- 4. Search for and open the Apache Felix Event Admin Implementation file.
- 5. Set the **Timeout** to 15000.
- 6. Close Apache Felix Event Admin Implementation.
- Locate and open the Apache Sling GET Servlet configuration, then verify that JSON Max Results is set to a minimum of 1000.
- 8. Close the Apache Sling GET Servlet.
- 9. Locate and open the **Day CQ Link Externalizer** configuration, then verify that the local domain URL matches the domain and port of AEM author access to facilitate the **Preview Feature**.

- 10. Close the Day CQ Link Externalizer configuration.
- 11. Locate and open CRXDE Lite.
- 12. Do one of the following:
 - If AEM 6.4 or 6.5—Remove
 - o /etc/workflow/models/globallink-adaptor-* and
 - o /etc/workflow/scripts/globallink-adaptor
 - If AEM 6.3—Remove
 - o /var/workflow/models/globallink-adaptor-* and
 - o /apps/workflow/scripts/globallink-adaptor
- 13. Verify:
 - a) Removal of /libs/globallink-adaptor/
 - b) Restoration of repositories and submissions from old version
 - /apps/globallink-adaptor/config/repositories/
 - /apps/globallink-adaptor/submissions/

The AEMP adaptor is installed.



If you receive a CSRF error when attempting to view the GlobalLink UI, add:

http://<aem_url>/(bin|apps)/globallink-.*

Apache Sling Referrer Filter > Allow Regexp Host and restart your AEM instance.

Install the Touch Editor Module

The Touch Editor module is an independent module used to submit content from the Touch Editor in AEM.

To install the module:

- 1. Go to the Package Manager.
- 2. Upload the GlobalLink Connect Plus Touch Editor x.x.x package into your AEM instance.
- 3. Click Install.

Configure AEM Dispatcher Module

If you are using **AEM Dispatcher** as a caching or load balancing tool, you can filter the adaptor path to prevent it always being cached on AEM. This eliminates adaptor upgrades and changes from being replicated in the Dispatcher configuration.

To install the Dispatcher module:

1. Open the **AEM Dispatcher** filter configuration, file and add:

```
/0007
{
    /glob "/apps/globallink-adaptor/*"
    /type "deny"
}
```

2. Save and close the file.

The adaptor is whitelisted on the **AEM Dispatcher** configuration.

Uninstall the Adaptor

To uninstall the adaptor:

- 1. Go to Package Manager > GlobalLink package.
- 2. Click Uninstall.

The adaptor is uninstalled.

5. Assign Non-Admin User Permissions


After you have installed the adaptor, you must assign permissions to all non-administrator users.

To assign non-administrator user permissions:

1. Go to:

http://

- 2. Search for groups or users using the search bar.
- 3. Double-click the group or user to open the user information in the right pane.
- 4. On the **Permissions** tab, select **Read** permissions—at the minimum—to the /apps/globallink-adaptor folders.



The user permissions are assigned.

6. AEMP Adaptor Configuration

You can configure your AEMP adaptor through the Configuration page.

Configure General Connection Settings

You can configure the connection between the adaptor and Project Director (PD).

If your site requires different configurations, you can create additional repositories defined by unique root paths. Any content that does not belong to a user defined repository retains default repository settings.


To configure general connection settings:

1. On the **AEM Navigation Pager** dashboard, click **Configuration**.



2. On the **Configuration** dialog, click the **General** tab.

3. Enter data in the general adaptor configuration option fields.



Required fields are marked with a red asterisk.

Field	Action
Web Services URL	Enter the URL for the PD instance that is connected to AEM followed by / services, such as, https://yourPDserver.translations.com/PD/services.
Username	Enter your PD instance credentials for creating submissions.
Password	Enter the PD user password.
Scheduler period	Select the frequency in minutes to for AEM to poll PD for completed submissions.
Submissions per import	Select the number of submissions in each import for AEM to poll PD for completed submissions.
Environment	Select client AEMP environment connection source as: Dev , QA , Staging , or Production
Append daytime to client identifier	Select to enable automatic PD cancellation of old submissions when you submit a new version.

4. Click Action > Save.



The general connection settings are configured.

Configure Proxy Server Settings

You can configure a proxy server for the adaptor and Project Director (PD) interaction.


If your site requires different configurations, you can create additional repositories defined by unique root paths. Any content that does not belong to a user defined repository retains default repository settings.

To configure a proxy server:

1. On the AEM Navigation Pager dashboard, click Configuration.




2. On the Configuration dialog, click the Proxy tab.



Required fields are marked with a red asterisk.

Field	Action
Enable proxy server	Select to enable the proxy server.
Host	Enter your proxy server host name.
Port	Select your proxy server port number.
Username	Enter your user ID for proxy authentication.
Password	Enter password for proxy authentication.

3. Click Actions > Save.



The proxy server settings are configured.

Configure Dashboard Appearance Settings

You can configure the appearance of the adaptor dashboard.




If your site requires different configurations, you can create additional repositories defined by unique root paths. Any content that does not belong to a user defined repository retains default repository settings.

To configure the dashboard appearance:

1. On the AEM Navigation Pager dashboard, click Configuration.



2. On the **Configuration** dialog, click the **Appearance** tab.



Required fields are marked with a red asterisk.

Field	Action
Repositories per page	Select the number of repositories visible on a given page.
Submissions per page	Select the number of submissions visible in a page.
	Note: Multiple targets within one submission are counted as a single submission.
TM updates per page	Select the number of translation memory (TM) updates visible on a given page.
Synchronization Jobs per page	Select the number of synchronization jobs visible on a given page.

3. Click Action > Save.



The dashboard appearance settings are configured.


Configure Log Setting

You can configure the logging level for each repository.


If your site requires different configurations, you can create additional repositories defined by unique root paths. Any content that does not belong to a user defined repository retains default repository settings.

To configure the logging level for a repository:

1. On the **AEM Navigation Pager** dashboard, click **Configuration**.



2. On the **Configuration** dialog, click the **Log** tab.




Required field is marked with a red asterisk.

Log Level Select log level to be downloaded. The options are **Info** and **Debug**.

Preview Log Click to preview the current log.

Download Log Click to download the current log to your download folder.

3. Click Actions > Save.



The logging level is configured.

Configure Users Setting

You can specify which users can view specific submissions using the **Users** option on the **Configuration** page.


If your site requires different configurations, you can create additional repositories defined by unique root paths. Any content that does not belong to a user defined repository retains default repository settings.

To configure user settings:

1. On the AEM Navigation Pager dashboard, click Configuration.



2. On the Configuration dialog, click the Users tab.




Enable submission user filtering List of user names Select to filter user names that should see all submissions.

Enter the IDs of those users with visibility to all submissions.



Those users not listed here can only see their submissions on the dashboard.

3. Click Actions > Save.



The user settings are configured.

Configure Preview Server Settings

You can configure your preview server settings.


- Contact your GlobalLink representative for your PSS URL, PSS Username, PSS Password, Org ID, and Client ID identifiers. These identifiers are unique to your account.
- If your site requires different configurations, you can create additional repositories with unique root paths. Any content that does not belong to a user defined repository retains default repository settings.
- Make sure that your entries contain no blank spaces before saving them.

To configure preview server settings:

1. On the AEM Navigation Pager dashboard, click Configuration.




2. On the Configuration dialog, click the Preview Server tab.



Field	Action
Preview Server URL	Enter the URL of the Preview Server instance that hosts the preview of the HTML pages sent for translation:
	• Staging —https://connect-dev.translations.com/api/v1/file/context/upload
	• Production —https://connect.translations.com/api/v1/file/context/upload
PSS User	Enter the preview server user ID.
PSS Password	Enter the preview server password.
Org ID	Enter the unique token identifier for your preview server.
Client ID	Enter the unique token identifier being the Org ID joined by a forward slash ("/") to your Client ID for use as a connection key to your preview server.
AEM User	Enter an AEM user ID with administrator permission, used to impersonate the fetching of each HTML page during submission creation.
AEM Password	Enter an AEM user password.

Field	Action
Additional value to the end of AEM page url to be previewed	(Optional) Enter any parameters to be passed with the URL for use in assembling the preview. For example, <i>?wcmdisabled=true</i> .
Remove preview packages after submission creation	Select to remove ZIP files with the pages preview after the submission is created and sent.

3. Click Actions > Save.



The preview server settings are configured.

Configure Preview Server Filter

You can configure your preview server to exclude selective files in the preview snapshot.

To configure preview server filters:

- 1. In CRXDE, browse to /apps/globallink-adaptor/config/.
- 2. Create an nt:unstructured node named pss.
- 3. On this **pss** node, create a **String[]** property named *ignoreFiles*.
- 4. Add your list of file names or name-patterns for exclusion.

For example:

- etc_designs_refresh_assets.js
- connect.facebook
- 5. Save the changes in CRXDE.

The preview server filters are configured.

Configure Workflows Setting

You can configure your specific workflow folder to customize the Workflow on Delivery list.


Contact your GlobalLink representative for your PSS URL, PSS Username, PSS Password, and Client ID identifiers. These identifiers are unique to each client.

To configure a workflow model connection settings:

1. On the AEM Navigation Pager dashboard, click Configuration.



2. On the **Configuration** dialog, click the **Workflows** tab.



- Enter your workflow models path for AEMP to use. If this workflow path is blank, AEMP lists all workflow models.
- 4. Click Actions > Save.



The workflow model connection settings are configured.


Configure Permissions Setting

You can configure permissions, for the specific Project Director (PD) projects, by users and usergroups.


Contact your GlobalLink representative for the list of project shortcodes that you need to assign permissions. These project codes are unique to each client.

To configure permissions by users and usergroups:


1. On the AEM Navigation Pager dashboard, click Configuration.



2. On the **Configuration** dialog, click the **Permissions** tab.



- 3. Enter the submitter user names (such as, *username1*) and usergroups (such as, *AEM000024,AEM000027*) in to the **Enter the users and project shortcodes to delegate permissions.** input area.
- 4. Click Actions > Save.



The permissions by user and usergroup are configured.



These permissions are visible when users create submission requests.



If you activate this feature, make sure that every user name and usergroup intended to configure and create submissions is listed here with appropriate projects codes assigned.

7. AEMP Site Repository Configuration


You can configure the AEMP site repository through the Repositories page.

Configure General Repository Settings


You can configure the general settings for each repository.

To configure the repository general settings:

1. On the AEM Navigation Pager dashboard, click Repositories.



- 2. In the **Repositories List**, select a repository, then click **Edit**.
- 3. On the Edit Repository Configuration dialog, click the General tab, then enter the settings.



Required fields are marked with a red asterisk.

Setting	Action
Repository path	Verify the auto-populated repository path.
Default submission name pattern	Enter the default name pattern for submissions as a function of the path to the page. Content between the forward-slashes refers to the current folder in the pathname. A hyphen after the slashes acts as a separator, using the following dot schema:
	 None—Exclude the submitted page name One—Include the submitted page name Three—Include the submitted page name and number of parent page names equal to the total number of dots For example: /// Locate results in the submitted page path: /content/geometrixx/en/products/mandelbrot/overview name: geometrixx_mandelbrot-overview.
Default submission status	 NOT READY—Submissions are created but not sent to PD immediately. You are given time to review and make changes before sending the submission to PD. READY—Submissions are created and sent immediately to PD.
Project name	Enter the default Project Director (PD) project name for the submissions.
Default Classifier	Enter the default file classifier.
Workflow on delivery	Select the workflow that must be triggered upon return of the translation to AEM, such as Adobe PLW.
Target rules	Set rules to determine how the adaptor selects the target path of a translated component. You can set target rules to replace a part of the path with a different value depending on the target language. For example: • \$PATH variable—Page, Experience fragments, DAM assets, i18n, and commerce translation use \$PATH(@replace(\$SRC_LANG, \$TGT_LANG)) to replace the source with the target locales to allocate the translations in the respective target folders on the specified path. For additional extended use cases, see, Extend Target Rules. • \$FILE_NAME variable—The DAM Metadata translation uses \$FILE_NAME(@replace(\$EXTENSION, -\$TGT_LANG \$EXTENSION)) • \$PROPERTY variable—The tags translation uses \$PROPERTY(@replace(\$PROPERTY, \$PROPERTY.\$TGT_LANG))

Setting	Action
Ignore Node with	List a value and property that protects the content of these nodes and their children from the translation process instead of blocking a single property.
Sort page nodes alphabetically on submission creation screen	Select to list the tree items alphabetically on the submission create page.
Sort pages by modified date on submission creation screen	Select to list the tree items from newest to oldest modified date.
Activate Split Submission by default	Select to have the Split Submission option selected by default on the submission create page.
Use sling:key to show dictionary items on the content tree	Select to display the sling:key property based dictionary items on the content tree.

4. Click Actions > Save.




The general repositories settings are configured.

Configure Resources Settings


You can configure the resource settings for each repository.

To configure a repository resource settings:

1. On the AEM Navigation Pager dashboard, click Repositories.



- 2. In the Repositories List, select a repository, then click Edit.
- 3. On the **Edit Repository Configuration** dialog, click the **Resources** tab, then enter the settings.



Setting	Action
Copy to target (Update)	Select to copy, after submission delivery, any translatable components from the source that do not exist in the target.
Copy all of the non- translatable fields during import	Select to copy all components that cannot be translated, from the source to the target after submission delivery, synchronizing pages.
Copy to target exceptions	Enter a list of specific adaptor nodes' properties or paths to omit coping from the source to the target: • Use propertyName • Use path patterns, such as, */cq:LiveSyncConfig/
Always copy properties (propertyName@*)	 Enter non-translatable properties to synchronize between source and target: Use propertyName@sling:resourceType If a property has no sling type, use propertyName@*
Delete resources on target, if they don't exist on source	(Optional) Select to delete properties on the target page that are not on the source page when a submission is delivered.

Setting	Action
File path with translatable Properties and resource type mapping	Enter the system path location for translatable components.
	Note: The resource must contain a UTF-8 text file without a bill of materials (BOM).
Custom List Of translatable properties and resource type mapping	Specify the list of translatable fields of AEM resources being sent to Project Director (PD) for translation. This section allows you to specify the translatable resources without the need to use a configuration file. Entries should be one per line in the following format:
	The propertyName@sling:resourceType
	• If the sling type is not in the same node as the propertyName, enter the path to it, such as, parentNode/propertyName@sling:resourceType.
	 Enter paths used to restrict a translatable property to certain pages, such as, pageName/body/leftCol/text@sling:resourceType.
	 Enter wildcards for use in generalizing the configuration, such as, text@* or products/*/label*@*
	 If a property has no sling type, enter propertyName@* or propertyName@**
	 If a property has multiple attributes in JSON format, you can map them by entering:
	propertyName@"attributeName1":"@"@*
	propertyName@"attributeName2":"@"@*
	
Always copy property	(Optional) Select to copy all translatable property values from the source in the
value into the target page during export	target pages when sending a submission.
Always copy to target for	(Optional) Select to copy all selected pages after submission delivery, including
pages without translatable fields during import	those pages with no content to translate.

4. Click Actions > Save.



The repository resource settings are configured.


Configure Blocked Resources Settings

To configure blocked resources settings:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repositories.



- 3. In the Repositories List, select a repository, then click Edit.
- 4. On the Edit Repository Configuration dialog, click the Blocked Resources tab, then enter your settings.



Setting	Action
Blocked resource types file path	Enter this file path to override any configuration set for the Blocked resource type in the user interface.
	Note: Use this method of blocking to include all properties listed in grey in the user interface display of your file.
Custom blocked resource type mapping	Enter the type of resources or resource paths in AEM restricted from submissions sent to Project Director (PD).
	Note: This entry allows the user to specify the non-translatable resources without the need to use a configuration file.
Block following nodes to be synced up on import	Enter the source nodes on AEM not synchronized with target nodes on import.
Block following nodes/ properties not to be deleted on import	 Enter the paths for nodes from the target that do not exist in the source that the adaptor does not delete. Enter the type of AEM resources for nodes from the target that do not exist in the source that the adaptor does not delete. Note: This only applies when Delete resources on target, if they don't exist
	on source is selected.
Block import on Nodes/ properties by filter: (propertyName=value)	Enter filters to block importing translated content on specific nodes. The adaptor looks for the target node property name in one of the nodes and, if matched, it prevents the content import.
Include blocking children nodes of parent that has the filter	Select to allow extending the blocking of content import on the children nodes from the blocked parent nodes as defined in Block import on Nodes/ properties by filter above.

5. Click Actions > Save.



The blocked resources settings are configured.


Configure Tags Settings

To configure the tags settings:


- 1. On the **AEM Navigation Pager** dashboard, click **GlobalLink Translation**.
- 2. Click Repositories.



- 3. In the Repositories List, select a repository, then click Edit.
- 4. On the **Edit Repository Configuration** dialog, click the **Tags** tab.



Setting	Action	
Copy tags to target (update)	Select to enable the copy of source tags to the target.	
Send tags to translation	Select to send translating standard jcr:tags or automatically create missing target tags during the GlobalLink translation update workflow.	
Tag types mapping file	Enter the file path with standard tags.	
path	Note: If a tag-types mapping file path is entered, the Custom tag types mapping is ignored.	
Custom tag types mapping	Enter non-standard tags that should be translated.	




The tags settings are configured.

Configure Tag Repositories


If you want to be able to submit tags for translation, you must configure the tag repositories.

To configure tag repositories:

1. On the AEM Navigation Pager dashboard, click Repositories.




- 2. In the **Repositories List**, select a content site repository, then click **Create**.
- 3. On the **New Repository** dialog, click the **General** tab.




Required fields are marked with a red asterisk.


- 4. Provide the following information:
 - Repository Path—Location path where the DAM assets folders are, such as,
 - **AEM 6.3**—/etc/tags
 - **AEM 6.4, 6.5**—/content/cq:tags
 - Target Rules—Rules the adaptor uses to allocate translations, in the form \$PROPERTY(@replace(\$PROPERTY,\$PROPERTY.\$TGT_LANG))
- 5. Click the **Resources** tab, then configure the **Custom resource type mapping** with the translatable fields.




6. Click the Languages tab, then configure each language mapping with source and target languages.



7. Click the Tags tab.



- 8. Select the following options:
 - Copy tags to target (update)
 - Submit tags to translation
 - (Optional) Custom Tag language mapping for localizing the tag property to a different locale for Adobe standards compliance
- 9. Click Actions > Save.



The tag repository is configured.

Configure References Settings

You can configure the handling of referenced components.


To configure the references settings:

1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.

2. Click Repositories.



- 3. In the Repositories List, select a repository, then click Edit.
- 4. On the **Edit Repository Configuration** dialog, click the **References** tab.



Setting Action

Send referenced pages to translation

Select to enable translation of referenced components when the referencing page is sent for translation. This causes the referenced component to be sent for translation and delivered to its target location.

If using **Send referenced pages to translation** and **Link Rewriting**, enter the following in the **Resources** configuration **Custom resource type mapping** entry field: path@foundation/components/reference.

Setting	Action	
Reference types mapping	Enter the file path with standard reference types.	
file path	Note: If a reference types mapping file path is entered then the Custom reference types mapping will be ignored.	
Custom reference types mapping	Enter your non-standard reference types.	
Children levels deep	Enter the number of levels for recursively searching the page for references. This defaults to one.	
Consider references with the following filters	Enter the fields for filtering the page references.	



The references settings are configured.

Configure Languages Settings


You can configure language mapping for each repository.

To configure repository languages:

- 1. On the **AEM Navigation Pager** dashboard, click **GlobalLink Translation**.
- 2. Click Repositories.



- 3. Select a repository, then click **Edit**.
- 4. On the **Edit Repository Configuration** dialog, click the **Languages** tab.



Setting	Action	
Language mapping file	Enter the path to the language mapping file.	
	Note: If a language mapping file is entered then the Custom language mapping is ignored.	
Custom language mapping	(Optional) Enter specific language codes in the format <i><display name="">@<aem code="">@<pd code=""></pd></aem></display></i> . Examples:	
	 English@en@en-US German@de@de-DE French@fr@fr-FR Note: Both the AEM and Project Director (PD) codes are case-sensitive. 	
Enable Workflow Target Languages	Select to enable the auto-translation workflow.	
Workflow Target Languages	Enter languages for the auto-translation workflow, such as French@fr-FR.	



The languages settings are configured.

Configure Auto Submission Settings

You can specify the handling of automated submissions.


To configure auto submission settings:

- 1. On the **AEM Navigation Pager** dashboard, click **GlobalLink Translation**.
- 2. Click Repositories.



3. In the Repositories List, select a repository, then click Edit.


4. On the Edit Repository Configuration dialog, click the Auto Submission tab.



Required field is marked with a red asterisk.

Setting	Action	
Root path	Enter the AEM node path for auto submission after creation or modification.	
Туре	Select a submission type:	
	Single—Sends only the modified root path page	
	Recursive—Sends the modified root path page and all child pages	
Set Time	Specify your submission scheduling:	
	Specific Time—Select to use a specific time.	
	Scheduler Period Select to use auto-submission.	
Scheduler Period	Select the frequency in minutes to have AEM poll PD to automatically submit content. Leave this blank if you are not using auto-submission.	
	Note: This is only effective if Set Time is Scheduler Period .	
Days	Select your auto-submission days and hours when you have selected Specific Time .	
Auto submission target languages	Enter the languages for target submissions. All languages should be listed in language mapping for the selected repository.	

Setting	Action	
Consider nodes with the following filters	List date filters or a property and value that, when included in a node, include the content of these nodes and their children in the translation.	
Ignore nodes with the following filters	List a property and value that, when detected in a target node, prevent any action on the target node and its children, not just a single property.	



The auto submission settings are configured.

Configure Notifications Settings

You can configure site repository notifications to provide submission status.



If your site requires different configurations, you can create additional repositories defined by unique root paths. Any content that does not belong to a user defined repository retains default repository settings.


Your configuration only applies to the selected repository.

To configure notifications settings:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repositories.



- 3. Select a repository, then click Edit.
- 4. On the Edit Repository Configuration dialog, click the Notifications tab.



Setting	Action
Send e-mails about successful send/receive for current repository	Select to enable notifications for successful send or receive submissions.
Send e-mails about errors in current repository	Select to enable submission error notifications.
Send e-mails to AEM user which created submission	Select to enable notifications to the AEM user creating submissions.
Recipients of adaptor messages	Enter e-mail addresses to receive notifications.



The notifications settings are configured.

Configure DAM Assets Settings


You can specify the handling of repository Digital Assets Management (DAM).

To configure repository DAM assets:

- 1. On the **AEM Navigation Pager** dashboard, click **GlobalLink Translation**.
- 2. Click Repository.




- 3. In the Repositories List, select a repository, then click Edit.
- 4. On the **Edit Repository Configuration** dialog, click the **DAM Assets** tab.



Setting	Action	
Send DAM assets to translation	Select to send DAM metadata for translation. The translatable value should be a property under the node. For example, the description node has property en , which will be translated into property zh .	
Asset properties for translation	Enter asset properties for translation. For example, description or dc:description if the languages property of description is not already created.	
Send binary files to translation	Select to send the DAM file binaries for translation. This can be for files either inserted into a page or you can use the Resource Types page to select them separately.	

Setting	Action	
Binary file types with classifier	Enter the list of file types to be translated, in the format of jcr:mimeType@PDclassifier. To determine jcr:mimeType, refer to the jcr:content node of your original file. PDclassifier is the file type name configured in Project Director (PD).	
Secondary Binary file types to be included with Translation	Enter the list of additional file types, such as, thumbnails of a PDF file. Contact your GlobalLink representative for the entry format of the jcr:mimeType@PDclassifier in the file type name.	
Import and add target variations under the same content fragment	(Optional) Select to import the translated content on a variation of the content fragment according to the target locale.	



The DAM assets settings are configured.

Configure DAM Repositories


If you want to be able to submit assets for translation, you must configure the DAM repositories.

To configure DAM repositories:

- 1. On the **AEM Navigation Pager** dashboard, click **GlobalLink Translation**.
- 2. Click Repositories.



- 3. In the Repositories List, select a content site repository, then click Create.
- 4. On the **New Repository** dialog, click the **General** tab.



Required fields are marked with a red asterisk.

5. In the field **Repository Path**, enter the location path where the DAM assets folders are, such as:


```
/content/dam/we-retail
```

- 6. In the field **Target Rules**, enter the rules the adaptor uses to allocate translations:
 - If you have a language folder structure—

```
$PATH(@replace($SRC_LANG,$SRC_LANG))
```


If you intend the DAM translation to be in the same folder—

7. Click Actions > Save.




Your DAM assets settings are saved.

8. Click the Languages tab, then configure the various language mappings as source and target languages.



- 9. Click the **Dam Assets** tab, then modify the following fields:
 - Select **Send Dam assets for translation** and in **Asset properties for translation**, list the different metadata properties required for translation, such as, *dc:title*, *dc:description*
 - Select **Send binary files to translation** and in **Binary file types with classifier**, list the different metadata properties required for translation, such as:
 - image/jpeg@Non-parsable (image assets)
 - image/png@Non-parsable (image assets)
 - application/pdf@Non-parsable (pdf assets)
 - text/html@ClassifierName (content fragments)





The DAM repository is configured.

Configure DAM Workflow Wait Time

When importing translated content for DAM assets AEM triggers generic workflows. These generic workflows can take excessive time to execute, depending on the asset size. You can configure a wait time for DAM asset import.

To configure DAM workflow wait time:

- 1. In CRXDE, browse to /apps/globallink-adaptor/config/.
- 2. Create a node named customConfig.
- 3. Add the property named damWaitTime and set it to 90000.

This is the time in milliseconds that the adaptor is to wait for the DAM workflows to begin importing the each asset's content.

4. Save the changes in CRXDE.

The DAM workflow wait time is configured.

Configure Link Rewriting Settings

You can configure the repository to enable and specify the handling of link rewriting.


To configure repository link rewriting settings:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repositories.



3. In the Repositories List, select a repository, then click Edit.

4. On the Edit Repository Configuration dialog, click the Link Rewriting tab.



Setting	Action	
Enable Link Rewriting	Select to enable the rewrite of any links within property values with the source language code according to the target rules to include the target path instead. This only recognizes /content/ strings.	
Blocked Resources	Enter any resource properties that are not to be rewritten.	
Enable Custom Link Rewriting	Select to enable custom link writing. This recognizes link references in Rich text properties and multi-line properties.	

Setting	Action
Custom Link Mappings	Enter the specific properties for rewrite using the following syntax and pattern:
	• propertyName@startOfLink@endOfLink@sling:resourceType
	 property name—The first part of the pattern
	 beginning of a link—The second part of the pattern
	 end of a link—The third part of the pattern
	 sling:resourceType—The fourth and last part of the pattern
	For example:
	• Source—link:/en/page.html"
	Custom Link Config—property@"link":"@"@*
	• Source— <a a="" en="" href="=" page.html"<="">
	Custom Link Config—text@href="@"@*
Blocked Nodes from link rewriting (based on filters): (propertyName=value)	Enter filters to block link rewriting on specific nodes. The adaptor looks for the target node property name in one of the nodes and, if matched, it prevents the link rewriting.
Include blocking children node of parent that has the filter:	Select to allow extending the blocking of link rewriting on the children nodes from the blocked parent nodes as defined in Blocked Nodes from link rewriting above.
Allow Synchronization Jobs to Use Regular and Custom Link Rewriting:	Select this checkbox to have synchronization jobs use the link rewriting configuration.



The link rewriting settings are configured.

Configure TM Update Settings

You can configure TM update settings to automate updates to Project Director (PD) for a repository.

To configure TM update settings:

- 1. On the **AEM Navigation Pager** dashboard, click **GlobalLink Translation**.
- 2. Click Repositories.



- 3. In the Repositories List, select a repository, then click Edit.
- 4. On the Edit Repository Configuration dialog, click the TM Update tab.




Required field is marked with a red asterisk.

Enable TM update Select to enable automatic TM updates to Project Director (PD).

Project name Enter the default PD project name.

5. Click Actions > Save.



The TM update settings are configured.

Configure Workflow Review Settings


You can configure the repository to map AEM reviewer and publisher user groups to each target language and all be included in the delivery of workflows.

To configure workflow review settings:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repositories.




- 3. In the Repositories List, select a content site repository, then click Edit.
- 4. On the Add Repository Configuration dialog, click the Workflow Review tab.



Setting	Action
Enable Reviewers on workflow for translated content	Select to enable support for reviewers.
List of languages and user groups	Enter the language locale and list the AEM translation reviewing user groups. For example: de@reviewers-de fr@reviewers-fr Where de is the language locale and reviewers-fr is a valid AEM user group.
Enable Publishers on workflow for translated content	Select to enable support for publishers.

Setting	Action
List of languages and user groups	Enter the language locale and list the AEM translation
	publishing user groups. For example:
	de@publishers-de
	fr@publishers-fr
	Where de is the language locale and publishers-fr is a
	valid AEM user group.



The workflow review settings are configured.

Configure Commerce Settings

You can configure the repository to map AEM reviewer and publisher user groups to each target language to include them in the delivery of workflows.

To configure workflow review settings:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repositories.



- 3. In the Repositories List, select a content site repository, then click Edit.
- 4. On the **Add Repository Configuration** dialog, click the **Commerce** tab.



Enter a custom character string to show as the item name when creating a submission for commerce products.

5. Click Actions > Save.



The commerce settings are configured.

8. Extend Target Rules

You can extend the feature of target rules to apply to different scenarios.

If your source content is in an English Master folder such as,

```
/content/we-retail/language-masters/en/experience/arctic-surfing-in-lofoten
```

And the content needs to be translated into specific region folders, such as-

```
/content/we-retail/america/de/experience/arctic-surfing-in-lofoten
/content/we-retail/america/fr/experience/arctic-surfing-in-lofoten
```

To allocate the translations into the /content/america/ folder use the following target rule:

```
$PATH(@replace(language-masters/$SRC_LANG,america/$TGT_LANG))
```

If your source content is in an English Master folder such as,

```
/content/we-retail/language-masters/en/experience/arctic-surfing-in-lofoten
```

And the content needs to be translated into specific country folders per language, such as—

```
/content/we-retail/america/de/de/experience/arctic-surfing-in-lofoten
  (Germany Folder)
/content/we-retail/america/ca/fr/experience/arctic-surfing-in-lofoten
  (Canada Folder)
```

To allocate the translations for each AEM target locale, use the following target rules:

```
de:$PATH(@replace(language-masters/$SRC_LANG,de/$TGT_LANG))
fr:$PATH(@replace(language-masters/$SRC_LANG,fr/$TGT_LANG))
```

9. Workflows Configuration

You can configure custom workflows as well as AEM 6.3, 6.4, and 6.5 workflows to submit content for translation.

Create Custom Workflows

GlobalLink Project Director (PD) AEM Connect Plus includes a sample AEM workflow that triggers translations. You can use this as a template in creating custom workflows.

To create a custom workflow:


- 1. Go to CRXDE.
- 2. For AEM 6.3, open the file:

```
http://localhost:4502/crx/de/index.jsp#/etc/workflow/scripts/globallink-adaptor/globallink-adaptor-test.ecma
```

3. For AEM 6.4 and 6.5, open the file:

```
http://localhost:4502/crx/de/index.jsp#/apps/workflow/scripts/globallink-adaptor/globallink-adaptor-test.ecma
```


- 4. Modify the English and target locales in accordance with your repository configuration.
- 5. Modify the PD project code.




- 6. Save your changes.
- 7. Go to:

http://localhost:4502/libs/cq/workflow/admin/console/content/models.html

8. Select the installed workflow, then click Edit.




9. On the Workflow modeler, select the **GlobalLink Translation** step and click ...



- 10. Click **Process Step**, then select a step property:
 - a) GlobalLink Translation (Single) Granite—Select to submit the content of one page for translation.

- b) **GlobalLink Translation (Recursive) Granite**—Select to submit the content of a page and sub-pages for translation in one single file.
- c) **GlobalLink Translation (Recursive Split) Granite**—Select to submit the content of a page and subpages for translation in separate files.



11. Click Done.


The custom workflow is created.

Test Custom Workflow


You should test your new custom workflow.

To test your workflow:


1. Select the workflow, then click Start Workflow.



2. On the Run Workflow dialog, search for and select Payload.




3. On the **Select Path** dialog, select the actual path of your custom workflow.



4. Click OK.

5. Click Run Workflow.

The submission is created and listed on the dashboard under the name of the root path.



10. Create i18n Dictionary Repositories

You can create and maintain your own, private internationalization (i18n) dictionary.

To create an i18n dictionary:

- 1. Create a repository with the dictionary root as its path.
- 2. Configure sling:message@** as the translatable resource.

The i18n dictionary repository is created.

Configure i18n Dictionaries as JSON Files

When your private dictionary has a JSON file structure, you must configure it for translation.

To configure your JSON dictionary:

- 1. Create a repository with the dictionary root as its path.
- 2. Configure the target rule:

```
$FILE_NAME(@replace(($SRC_LANG$EXTENSION, -$TGT_LANG$EXTENSION))
```

3. Save the repository.

The i18n dictionaries are configured as JSON Files.

11. Configure Error Notifications

To provide error related email notifications, the AEM email settings must be configured as described:

1. Go to:

http://localhost:4502/system/console/configMgr/com.day.aem.mailer.DefaultMailService

2. Enter the parameters listed in the following table.

Parameters	Description
SMTP Server Host	Enter your provider's host name. For example, Gmail SMTP is smtp.gmail.com
Name	
SMTP Server Port	Enter a user e-mail address.
SMTP Password	Enter the user account password.
FROM Address	Enter the e-mail address for use in the From: field.
Gmail Config	Select SMTP use SSL.
Emitter Config	Select Send Emails and enter the e-mail addresses.

Every email addressee receives one email per error. Email notifications may not work on non-Windows installations.

12. Configure Adaptor Logs

To configure your adaptor logs, you must modify the paths in the following two properties files:

1. Edit the path stored in the following properties file:

```
/apps/globallink-adaptor/config/
    org.apache.sling.commons.log.LogManager.factory.config-PD2/
    org.apache.sling.commons.log.file
```

2. Edit the path stored in the following properties file:

```
/apps/globallink-adaptor/config/
org.apache.sling.commons.log.LogManager.factory.writer-PD2/
org.apache.sling.commons.log.file
```

The adaptor logs are configured.


13. Content Fragments Configuration

To permit the adaptor to include the CMS content fragments, you must configure the **Content Fragments** as described here using the **Edit Repository Configuration** dialog.


Include CMS AEM 6.3.0 Fragments

To include CMS AEM 6.3.0 fragments:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repository.



- 3. In the Repositories List, select a content site repository, then click Edit.
- 4. On the Edit Repository Configuration dialog, click the DAM Assets tab.



- 5. Select the Send binary files to translation.
- On the Binary file types with classifier enter text/html@PDclassifier.
 Where, PDclassifiier is the file type name as configured in Project Director (PD).
- 7. Click Actions > Save.



The content fragments from AEM 6.3.0 are set for inclusion in submissions.

Include CMS AEM 6.4.0 and 6.5.0 Fragments


To include CMS AEM 6.4.0 and 6.5.0 fragments:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repository.



3. In the Repositories List, select a content site repository, then click Edit.

4. On the Edit Repository Configuration dialog, click the DAM Assets tab.



- 5. Select the Send DAM assets to translation.
- 6. On the **Asset properties for translation**, enter the content fragment properties needed for translation.

These properties are found in:

/content/dam/we-retail/en/experiences/arctic-surfing-in-lofoten/
arctic-surfing-in-lofoten/jcr:content/data/master

7. Click Actions > Save.



The CMS AEM 6.4.0 and 6.5.0 fragments are set to be included in submissions.

14. Experience Fragments Configuration

To permit the adaptor to include the CMS experience fragments, you must use the **Edit Repository Configuration** dialog.


Include Experience Fragments from Page

To include experience fragments within a page:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repository.




- 3. In the Repositories List, select a content site repository, then click Edit.
- 4. On the Edit Repository Configuration dialog, click the References tab.



- 5. Select the Send referenced pages to translation.
- 6. On the Custom references types mapping enter your experience fragment property path and resource type.
 For example:

fragmentVariationPath@gl_demo/components/content/experiencefragment

7. Click Actions > Save.



The page experience fragments are set for inclusion in submissions.

Configure Experience Fragments Repositories

If you want to submit experience fragments for translation, you must create a repository similar to a Site repository.


To configure experience fragment repositories:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repositories.



3. In the Repositories List, select a content site repository, then click Create.

4. On the **New Repository** dialog, click the **General** tab.



Required fields are marked with a red asterisk.

5. In the field Repository Path, enter the location path of the Experience Fragments folders, such as:

```
/content/experience-fragment/we-retail
```

6. In the field Target Rules, enter the rules the adaptor uses to allocate translations.

For example, for a language folder structure, enter:

```
$PATH(@replace($SRC_LANG,$SRC_LANG))
```

- 7. Click the Languages tab, and configure the required language mappings as source and target languages.
- 8. Click Actions > Save.



Your experience fragments repository is configured.

15. Campaigns Configuration

To permit the adaptor to include the CMS Campaign content, you must use the **Edit Repository Configuration** dialog.

Configure Campaign Repositories


If you want to be able to submit Campaign content for translation, you must use the **Edit Repository Configuration** dialog.

To configure Campaign content repositories:

- 1. On the AEM Navigation Pager dashboard, click GlobalLink Translation.
- 2. Click Repositories.



- 3. In the Repositories List, select a content site repository, then click Create.
- 4. On the **New Repository** dialog, click the **General** tab.



Required fields are marked with a red asterisk.

5. In the field Repository Path, enter the location path of the Campaign content folders, such as:

/content/campaigns/we-retail

6. In the field **Target Rules**, enter the rules the adaptor uses to allocate translations.

For example, for a language folder structure, enter:

\$PATH(@replace(\$SRC_LANG,\$SRC_LANG))

- 7. Click the **Languages** tab, and configure the required language mappings as source and target languages.
- 8. Click Actions > Save.



Your Campaign content repository is configured.

16. AEM Rollout Configuration

When configuring MSM on AEM, you can create an AEM custom rollout configuration to submit translation changes made from the source, Blueprint, to the target, the live copy.

Create a Custom Rollout on AEM 6.3.0

You can create a custom rollout for AEM 6.3.0.

To create a custom rollout:

1. Go to:

http://localhost:4502/miscadmin#/etc/msm/rolloutconfigs


- 2. Select Roll Configurations, then create a New Page and name it GlobalLink Rollout.
- 3. Go to crxde/msm at:

http://localhost:4502/crx/de/index.jsp#/etc/msm/rolloutconfigs


- Expand Pushonmodify > jcr:content.
- 5. Copy all child pages from here to GlobalLink Rollout.
- 6. Select jcr:content and create a new node called workflow. You must set this to cq:LiveSyncAction.
- 7. Create one more property named target with the value:

/etc/workflow/models/globallink-adaptor/globallink-translationsingle-granite/jcr:content/model

8. Click Properties on one of the Live Copy sites on AEM.



9. Click the Live Copy tab and un-select Inherit Rollout Configs from Parent, then select GlobalLink Rollout configuration from the Rollout Configs list.



10. Save all the changes.

The custom rollout is created.

Create a Custom Rollout on AEM 6.4.0 and 6.5.0

You can create a custom rollout for AEM 6.4.0 and 6.5.0.

To create a custom rollout:

1. Go to:

http://localhost:4502/crx/de/index.jsp#/libs/msm/wcm/rolloutconfigs


- 2. Create a new node of type cq:RolloutConfig, naming it GlobalLink Rollout.
- 3. Go to GlobalLink Rollout and create the properties:
 - cq:trigger and set it to rollout
 - jcr:title and set it to GlobalLink Rollout




- 4. Save CRXDE.
- 5. Expand Pushonmodify > jcr:content and copy all child pages to GlobalLink Rollout.
- 6. Select **jcr:content**, then create a new node called *workflow* and set it to *cq:LiveSyncAction*.
- 7. Create one more property named **target** and set it to:

/var/workflow/models/globallink-adaptor/globallinktranslation-single-granite/

8. Click Properties on one of the Live Copy sites on AEM.



 Click the Live Copy tab, then un-select Inherit Rollout Configs from Parent and select the GlobalLink Rollout configuration from the Choose Rollout Config drop-down list.



10. Save all the changes.

The custom rollout is created.